

PASO A PASO PARA MINAR



ONIX


Desde GPU's

Paso 1


The screenshot shows a Windows File Explorer window titled 'sph-sgminer_x11mod'. The address bar shows the path 'sph-sgminer_x11mod'. The left sidebar shows the 'Favoritos' section with 'Descargas' selected. The main pane displays a list of files and folders in a table format. The file 'sgminer.conf' is highlighted in blue. A red arrow points to this file from the right, with the text 'Seleccionar el archivo señalado y hacer clic Derecho'.

| Nombre | Fecha de modificación | Tipo | Tamaño |
|--|-----------------------|-------------------------|----------|
| kernel | 24/05/2014 12:44 | Carpeta de archivos | |
| libcurl-4.dll | 24/05/2014 12:43 | Extensión de la apli... | 608 KB |
| libeay32.dll | 24/05/2014 12:43 | Extensión de la apli... | 1.665 KB |
| libgcc_s_dw2-1.dll | 24/05/2014 12:43 | Extensión de la apli... | 110 KB |
| libidn-11.dll | 24/05/2014 12:43 | Extensión de la apli... | 274 KB |
| libpdcurses.dll | 24/05/2014 12:43 | Extensión de la apli... | 146 KB |
| pthreadGC2.dll | 24/05/2014 12:43 | Extensión de la apli... | 117 KB |
| sgminer.conf | 25/05/2017 15:39 | Archivo CONF | 2 KB |
| sgminer | 03/06/2014 21:28 | Aplicación | 1.174 KB |
| ssleay32.dll | 24/05/2014 12:43 | Extensión de la apli... | 356 KB |
| x11modGeForce GT 520glg2tc8192w256l4.bin | 25/05/2017 15:19 | Archivo BIN | 1.979 KB |
| zlib1.dll | 24/05/2014 12:43 | Extensión de la apli... | 111 KB |

Paso 2



Paso 3



Archivo Editar Buscar Ver Formato Lenguaje Configurar Macro Ejecutar TextFX Plugins Ventanas ?

sgminer.conf

```
1 {
2   "pools" : [
3     {
4       "url" : "stratum+tcp://104.131.189.125:3032",
5       "user" : "XSoG4iYqig32EPav4UiLc6yWkRTpzmTtYj",
6       "pass" : "1"
7     },
8     {
9       "url" : "stratum+tcp://104.131.189.125:3008",
10      "user" : "XSoG4iYqig32EPav4UiLc6yWkRTpzmTtYj",
11      "pass" : "1"
12    },
13    {
14      "url" : "stratum+tcp://104.131.189.125:3256",
15      "user" : "XSoG4iYqig32EPav4UiLc6yWkRTpzmTtYj",
16      "pass" : "1"
17    }
18  ]
19 }
20 ,
21 "intensity" : "18",
22 "worksize" : "256",
23 "kernel" : "x11mod",
24 "lookup-gap" : "2",
25 "thread-concurrency" : "8192",
26 "shaders" : "0",
27 "gpu-threads" : "1",
28 "gpu-engine" : "0-0",
29 "gpu-fan" : "0-0",
30 "gpu-memclock" : "0",
31 "gpu-memdiff" : "0",
```

Configuracion del pool con su distintos puertos.


Asegurate de colocar tu direccion Wallet en los 3 bloques editando las lineas por ejemplo:

```
"user" : "XSoG4iYqig32EPav4UiLc6yWkRTpzmTtYj",
```

Asignar la Cantidad de Tarjetas de Video Disponibles para el minado.

Normal text file | length : 1090 lines : 52 | Ln : 27 Col : 21 Sel : 0 | Dos\Windows ANSI INS

Paso 4




Una vez configurado todo según las instrucciones en los pasos anteriores Guardamos el archivo.


```
104.131.189.125:3032",
:Pav4UiLc6yWkRtpzmItYj",
104.131.189.125:3008",
:Pav4UiLc6yWkRtpzmItYj",
104.131.189.125:3256",
:Pav4UiLc6yWkRtpzmItYj",
20
,
21 "intensity" : "18",
22 "worksize" : "256",
23 "kernel" : "x11mod",
24 "lookup-gap" : "2",
25 "thread-concurrency" : "8192",
26 "shaders" : "0",
27 "gpu-threads" : "1",
28 "gpu-engine" : "0-0",
29 "gpu-fan" : "0-0",
30 "gpu-memclock" : "0",
31 "gpu-memdiff" : "0",
```

Normal text file | length : 1090 lines : 52 | Ln : 27 Col : 19 Sel : 0 | Dos\Windows | ANSI | INS

Paso 5



Paso 6



The screenshot shows a Windows File Explorer window titled "sph-sgminer_x11mod" with the address bar set to "sph-sgminer_x11mod". The main pane displays a folder named "sph-sgminer_x11mod" containing a file named "sgminer.exe". A red box highlights the terminal window that opens when "sgminer.exe" is executed. The terminal output is as follows:

```
sgminer 4.1.0 - Started: [2017-05-26 15:33:59] - [0 days 00:09:13]
-----
<5s>:120.6K <avg>:120.3Kh/s ! A:3 R:0 HW:0 WU:0.002/m
ST: 2 SS: 0 NB: 1 LW: 449 GF: 0 RF: 0
Connected to 104.131.189.125:3032 (stratum) diff 0.001 as user XSoG4iYqig32EPav4
Block: 5f6cf102... Diff:0 Started: [15:33:59] Best share: 0.108
-----
[P]ool management [G]PU management [S]ettings [D]isplay options [Q]uit
GPU 0:
! 120.5K/120.3Kh/s ! A:3 R: 0.0% HW:0 WU:0.002/m I:18
-----
[15:42:28] Accepted 4fa62d31 Diff 0.013/0.005 GPU 0 at Pool 0
[15:42:49] Accepted 09400036 Diff 0.108/0.005 GPU 0 at Pool 0
[15:43:01] Pool 0 difficulty changed to 0.001
```

A red arrow points from the terminal window to the text on the right: "Se debe mostrar esta pantalla una vez ejecutado el archivo".

Paso 7

Capacidad de Procesamiento y Capacidad Promedio de Procesamiento

```
sgminer 4.0.0 - Started: [2017-05-26 15:33:59] - [0 days 00:09:13]
-----
<5s>:120.6K (avg):120.3Kh/s A:3 R:0 HW:0 WU:0.002/m
SI: 2 SS: 0 NB: 1 LW: 449 GF: 0 RF: 0
Connected to 104.131.189.125:3032 (stratum) diff 0.001 as user XSoG4iYqig32EPav4
Block: 5f6cf102... Diff:0 Started: [15:33:59] Best share: 0.108
-----
[P]ool management [G]PU management [S]ettings [D]isplay options [Q]uit
GPU 0:
! 120.5K/120.3Kh/s ! A:3 R: 0.0% HW:0 WU:0.002/m I:18
-----
[15:42:28] Accepted 4fa62d31 Diff 0.013/0.005 GPU 0 at Pool 0
[15:42:49] Accepted 09400036 Diff 0.108/0.005 GPU 0 at Pool 0
[15:43:01] Pool 0 difficulty changed to 0.001
```

Indicador de aceptación y Felicidades ya estas Minando Onix.